

# Changing Sync Folder Locations on Client

Tonido Sync Folder locations can be changed manually on Tonido versions 2.34 and above by editing the configuration XML file. We only suggest doing this if you are comfortable editing files.

## Tonido Sync Client Folder DEFAULT Locations

	Windows	Mac OSX	Linux	TonidoPlug
<b>Sync Client Data Location</b>	%APPDATA%\TonidoSyncData\client	{HomeDir}\TonidoSyncData\client	{HomeDir}\TonidoSyncData\client	{UserDataDirectory}\TonidoSyncData\client
<b>Sync Folder</b>	{MyDocumentsFolder}\TonidoSync	{HomeDir}\TonidoSync	{HomeDir}\TonidoSync	{UserDataDirectory}\TonidoSync

### Config File Location

To change sync folder location, please open the `syncclientconfig.xml` file located in the following locations.

OS	Location
Windows	{TonidoSyncInstallDir}\syncclientconfig.xml Usually: %APPDATA%\TonidoSync\syncclientconfig.xml
Mac OSX	{HomeDir}\syncclientconfig.xml
Linux	{HomeDir}\syncclientconfig.xml
TonidoPlug	NA, See Server Settings

### XML format

```
<?xml version="1.0" encoding="UTF-8" ?>
<variantrow>
  <rowentry>
    <name>syncclientlocation</name>
    <type>string</type>
    <value>DEFAULT</value>
  </rowentry>
  <rowentry>
    <name>syncfolderlocation</name>
    <type>string</type>
    <value>DEFAULT</value>
  </rowentry>
</variantrow>
```

### How to Change

1. To change the locations, first shutdown Tonido Sync Client.
2. If you have been already syncing files in the default location, make sure to copy that folder to the new location.
3. Then replace the DEFAULT string with the full path to that folder in the `syncclientconfig.xml` file. For example, if your new sync folder location is `D:\TonidoSync`, replace the `syncfolderlocation` DEFAULT to `D:\TonidoSync`
4. Then restart the Tonido Sync Client application.
5. Test whether sync is happening correctly before removing the original location